Setting up your e-mail account on iOS

** The setup for iPad is similar.

Step 1: Go to **Settings**

Step 2: Scroll down a bit, tap **Passwords & Accounts**

Step 3: Tap **Add Account**

inCONCEPT

Step 4: Tap Other

Step 5:
Tap Add Mail Account

Step 6:
Enter your account details,
Then Tap **Next**

Note: Mail will try to find your email settings. After the account lookup completes, you will need to enter the email settings manually. Follow the steps below to finish your account setup.

CONCEPT

Step 7:
Choose **IMAP** for your new account

Step 8:
Enter **mx3.mailme.com.hk** as **Host Name**, Be sure to enter correct info for both parts. Tap **Next** to proceed.

Step 9:
After verification, leave the default settings and proceed by tapping **Save**

Cancel	New Account	Next

IMAP	POP

Name	[Your Name]
Email	[Your Email Address]
Description	

INCOMING MAIL SERVER

Host Name	mx3.mailme.com.hk
Username	[Your Email Address]
Password	[Your Password]

OUTGOING MAIL SERVER

Host Name	mx3.mailme.com.hk
Username	[Your Email Address]
Password	[Your Password]

Cancel	IMAP	Save

| ✉ Mail	⬤
📒 Notes	⬤

inCONCEPT

Step 10:
It will take you back to
Password and Accounts
Tap on the account you've just
created

Step 11:
Tap **Account** to proceed to the
next step

Step 12:
In the **Account**, Tap **SMTP**

‹ Settings **Passwords & Accounts**

ACCOUNTS

iCloud
iCloud Drive, Mail, Calendars, Safari and 6 more... ›

Exchange
Mail, Contacts, Calendars ›

Gmail
Mail, Contacts, Calendars ›

MailMe
Mail ›

Add Account ›

Fetch New Data Off ›

‹ Accounts **Oxmbx**

IMAP

Account username@mailme.com.hk ›

✉️ Mail 🟢

📝 Notes ⚪

Delete Account

Cancel **Account** Done

IMAP ACCOUNT INFORMATION

Name [Your Name]

Email [Your Email Address] ›

Description

INCOMING MAIL SERVER

Host Name mx3.mailme.com.hk

Username [Your Email Address]

Password ••••••••••••••

OUTGOING MAIL SERVER

SMTP mx3.mailme.com.hk ›

Advanced ›

Step 13:
Tap **mx3.mailme.com.hk**, which should be your Primary Server

Step 14:
Make sure **SSL** has enabled.
Authentication: Password
Server Port: 465

Step 15:
Tap **Done**, after verification, you will be taken back to **SMTP**, Tap ＜**Account**

‹ Account   **SMTP**

PRIMARY SERVER

mx3.mailme.com.hk   On ›

OTHER SMTP SERVERS

Add Server...   ›

If Mail is unsuccessful using the primary server, it will try the other SMTP servers in succession.

Cancel   **mx3.mailme.com.hk**   Done

Server   ⬤

OUTGOING MAIL SERVER

Host Name   mx3.mailme.com.hk

Username   [Your Email Address]

Password   ●●●●●●●●●●●●●

Use SSL   ⬤

Authentication   Password ›

Server Port   465

Delete Server

‹ Account   **SMTP**

PRIMARY SERVER

smtp.siteprotect.com   On ›

OTHER SMTP SERVERS

Add Server...   ›

If Mail is unsuccessful using the primary server, it will try the other SMTP servers in succession.

in CONCEPT

Step 16:
In **Account**, Tap **Advanced**

Step 17:
Scroll down to the buttom
Make sure **SSL** has enabled.
Authentication: Password
Server Port: 993

Cancel	Account	Done

IMAP ACCOUNT INFORMATION

Name	John Doe
Email	username@oxmbx.com >
Description	Oxmbx

INCOMING MAIL SERVER

Host Name	imap.siteprotect.com
Username	username@oxmbx.com
Password	••••••••••••••

OUTGOING MAIL SERVER

SMTP	smtp.siteprotect.com >

Advanced	>

‹ Account	Advanced

MOVE DISCARDED MESSAGES INTO:

Deleted Mailbox	✓
Archive Mailbox	

DELETED MESSAGES

Remove	After one week >

INCOMING SETTINGS

Use SSL	🟢
Authentication	Password >
IMAP Path Prefix	/
Server Port	993

Lastly, Tap ＜**Account**, then tap **Done**. Open Mail app and your email will be ready